

```

!
version 12.2
service timestamps debug uptime
service timestamps log uptime
no service password-encryption
!
hostname gruppe6Router
!
enable secret 5 $1$4b9g$f3Sorzk.a2faj50hl01ji/
!
ip subnet-zero
!
!
!
!
!
!
interface FastEthernet0/0
 ip address 172.16.6.1 255.255.255.0
 duplex auto
 speed auto
!
interface Serial0/0
 ip address 172.16.106.1 255.255.255.0
 clock rate 64000
!
interface FastEthernet0/1
 no ip address
 shutdown
 duplex auto
 speed auto
!
interface Serial0/1
 ip address 172.16.105.2 255.255.255.0
 clock rate 64000
!
ip classless
ip route 0.0.0.0 0.0.0.0 Serial0/1
ip route 172.16.1.0 255.255.255.0 Serial0/1
ip route 172.16.2.0 255.255.255.0 Serial0/1
ip route 172.16.3.0 255.255.255.0 Serial0/1
ip route 172.16.4.0 255.255.255.0 Serial0/1
ip route 172.16.5.0 255.255.255.0 Serial0/1
ip route 172.16.7.0 255.255.255.0 Serial0/0
ip route 172.16.8.0 255.255.255.0 Serial0/0
ip route 172.16.9.0 255.255.255.0 Serial0/0
ip route 172.16.10.0 255.255.255.0 Serial0/0
ip route 172.16.101.0 255.255.255.0 Serial0/1
ip route 172.16.102.0 255.255.255.0 Serial0/1
ip route 172.16.103.0 255.255.255.0 Serial0/1
ip route 172.16.104.0 255.255.255.0 Serial0/1
ip route 172.16.105.0 255.255.255.0 Serial0/1
ip route 172.16.107.0 255.255.255.0 Serial0/0
ip route 172.16.108.0 255.255.255.0 Serial0/0
ip route 172.16.109.0 255.255.255.0 Serial0/0
ip route 172.16.110.0 255.255.255.0 Serial0/0
ip http server
!
banner exec  Exec process created.
banner incoming  You're connecting to terminal-session of
gruppe6Router.
banner login  Access for authorized persons only.
banner motd  This is gruppe6Router.
banner prompt-timeout  Login canceld because of timeout.
!

```

```
line con 0
  password cisco
  login
line aux 0
line vty 0 4
  password cisco
  login
!
end
```