

```
!  
version 12.1  
no service pad  
service timestamps debug uptime  
service timestamps log uptime  
service password-encryption  
!  
hostname gruppe6Switch  
!  
enable secret 5 $1$wsXU$FHLKRz1eIY5twNnQtYn7K0  
!  
ip subnet-zero  
!  
ip ssh time-out 120  
ip ssh authentication-retries 3  
!  
spanning-tree mode pvst  
no spanning-tree optimize bpdu transmission  
spanning-tree extend system-id  
!  
!  
!  
!  
interface FastEthernet0/1  
!  
interface FastEthernet0/2  
!  
interface FastEthernet0/3  
!  
interface FastEthernet0/4  
!  
interface FastEthernet0/5  
!  
interface FastEthernet0/6  
!  
interface FastEthernet0/7  
!  
interface FastEthernet0/8  
!  
interface FastEthernet0/9  
!  
interface FastEthernet0/10  
!  
interface FastEthernet0/11  
!  
interface FastEthernet0/12  
!  
interface FastEthernet0/13  
!  
interface FastEthernet0/14  
!  
interface FastEthernet0/15  
!  
interface FastEthernet0/16  
!  
interface FastEthernet0/17  
!  
interface FastEthernet0/18  
!  
interface FastEthernet0/19  
!  
interface FastEthernet0/20  
!  
interface FastEthernet0/21  
!
```

```
interface FastEthernet0/22
!
interface FastEthernet0/23
!
interface FastEthernet0/24
!
interface Vlan1
 ip address 172.16.6.2 255.255.255.0
 no ip route-cache
!
ip http server
banner exec  You entered the USER-EXEC-MODE!
banner incoming  You are creating a terminal-session now.
banner login  You are about to log into this switch now. Please only
log in if you are authorized for access ... 
banner motd  This is the SWITCH of group 6 on Elektronikschule
Tettnang. Unauthorized access DENIED!
banner slip-ppp  You are establishing a connection via SLIP/PPP.
banner prompt-timeout  You were inactive too long. The switch has
closed your session automatically.
banner config-save  You are about to save new configuration-data. 
!
line con 0
 password 7 02050D480809
 login
line vty 0 4
 password 7 030752180500
 login
line vty 5 15
 login
!
!
end
```